



# **VMSS 2.0**

## **New Generation of Aupera Video Machine Learning Streaming Server**

### **Detailed User Guide**

**Document Revision: 2.1.0**

1	INTRODUCTION TO VMSS 2.0 .....	4
	1.1 VMSS2.0 PIPELINES .....	7
2	RUNNING VMSS2.0 ON VMACCEL .....	12
	2.1 LAUNCHING AUPERA VMSS2.0 INSTANCE ON VCK5000 .....	12
	2.2 USING VMSS2.0 WEB CLIENT .....	13
	2.2.1 ADD VIDEO STREAMS TO ACCESS APPLICATIONS .....	13
	2.2.2 RUNNING AUPERA'S CROWD FLOW APPLICATION .....	15
	2.2.3 RUNNING CUSTOM PIPELINES .....	25
	2.2.4 USING VIDEO STREAMS TO ADD NEW STREAM, PLAY VIDEOS, OR CHANGE SNAPSHOTS .....	35
	2.2.5 AI HOSTS PAGE .....	38
	2.2.6 USEFUL TOOLS .....	41
	2.3 USING VMSS2.0 SERVER (VIA COMMAND LINE) .....	44
	2.3.1 VMSS2.0 SERVER DOCKER .....	44
	2.4 LAUNCHING YOUR OWN RTSP STREAMS .....	47
3	RUNNING VMSS2.0 ON-PREMISES .....	48
	3.1 PREREQUISITES .....	48
	3.2 VMSS2.0 SERVER (AVAS) .....	48
	3.3 SETTING UP RTSP STREAMS .....	49
4	VMSS2.0 PIPELINES .....	52
	4.1 RUNNING VMSS2.0 PIPELINES .....	52
	4.2 PIPELINE EXAMPLES .....	52
5	AUPERA NODE TOOLKIT .....	61
	5.1 GRAPH-LEVEL CONFIGURATIONS .....	61
	5.2 NODE-LEVEL CONFIGURATIONS .....	62

---

5.3 NODES CURRENTLY INCLUDED IN AUPERA NODE TOOLKIT ....	64
5.3.1 STREAM DEMUX .....	64
5.3.2 VIDEO DECODER .....	65
5.3.3 STREAM MUX .....	65
5.3.4 VIDEO ENCODE .....	66
5.3.5 VIDEO FILTER .....	67
5.3.6 OBJECT (BOX) DETECTOR .....	68
5.3.7 OBJECT TRACKER .....	73
5.3.8 IMAGE CLASSIFIER .....	76
5.3.9 OBJECT (BOX) VISUALIZER .....	79
5.3.10 IMAGE STREAM CALCULATOR .....	82
5.3.11 VIDEO STREAM CALCULATOR .....	83

## **1 INTRODUCTION TO VMSS 2.0**

Video Machine-learning Streaming Server (VMSS) is a software application designed to function as a ‘server’ process to provide video analytic services to multiple video streams and efficiently utilize multiple FPGA resources on a server system.

VMSS 1.0 was released in early 2021(VMSS 1.X) that had certain limitations. The limitations prevented the user from building more flexible ML pipelines. For instance, how plugins pass data to other nodes, network branching, packet synchronization across branches of ML pipelines, and in-order processing of frames across several streams that share the same network.

The new generation of VMSS (VMSS 2.0) has eliminated these limitations by replacing plugins with graph nodes that can have arbitrary types (as opposed to just pre-processing, post-processing, ML, and database). These nodes support back edges (edges from downstream nodes to the upstream ones) and side packets (less frequent communication, available during initialization, before any packets are received); thus, allowing arbitrary (and even cyclical) graphs instead of just the linear graphs that the previous generation supports. In addition, users can now choose to not use a single job queue for streams that share the same network; thus, allowing for packets to be synchronized across multiple streams.

Most importantly, with VMSS 2.0 pipelines can be built, configured, and run using a graphical user-interface allowing customers to rapidly create new applications using both the collection of nodes provided in Aupera’s node toolkit; or by creating their own nodes with the aid of Aupera’s node creation framework. When using Aupera’s node toolkit, building most ML pipelines does not require any coding (or hardware knowledge). Furthermore, using the graphical user interface customers can try any of the models on

Xilinx Model Zoo (currently box detector and classifier models) with only a few mouse clicks.

VMSS 2.0 also provides a certain level of hardware abstraction (due to the higher modularity of nodes) which allows the same ML pipeline to run on different hardware platforms. This also allows for new hardware platforms to be adopted very quickly. Currently, pipelines built with VMSS 2.0 can run on VCK5000 acceleration cards (in addition to U50, U30, and AUPV205). In this release, we provide the VMSS 2.0 server along with a web-application that acts as the client (and visual GUI).

If you have additional questions and/or want to report an issue with your user experience, write to [vmss@aupera.com](mailto:vmss@aupera.com).

Vendor	Modified	Size	Container Version
Aupera	TBD	1.4GB	new_vmss_2.1.0
Aupera	TBD	1.43GB	vmss2.0.0_avac1.0.0

### Deployment Options

This application is containerized and can be easily run in a few minutes on VCK5000 cards on an on-premises servers or on pre-configured cloud instances.

On Premises	
VCK5000	<ul style="list-style-type: none"><li>Xilinx Runtime: <b>202120.2.12.427</b></li><li>Target Platform: <b>xilinx_vck5000_gen3x16_xdma_base_1</b></li></ul>

VMSS 2.0 consists of two major modules, Aupera Video AI Client (AVAC) and Aupera Video AI Server (AVAS). AVAC allows users to use a user-friendly GUI to connect to AVAS. Additionally, more advanced users may work with AVAS via the command line directly.

**NOTE:** We may use Aupera Video AI Client (AVAC) and Aupera's VMSS2.0 AI Client interchangeably throughout this document. We may also use Aupera Video AI Server (AVAS) and Aupera's VMSS2.0 AI Server interchangeably throughout this document.

The rest of this document is organized as follows:

Section 1.1 provides a brief introduction to VMSS2.0 pipelines.

Section 2.1 describes how to launch VMAccel instances that have both Aupera VMSS2.0 server and web client running.

Section 2.2 describes how to use the Aupera VMSS2.0 Web Client.

Section 2.3 describes how to use the Aupera VMSS2.0 Server via the command line.

Section 2.4 describes how to launch your own RTSP stream (optional).

Section 3.1 describes the prerequisites for installing and using VMSS2.0 on-premises.

Section 3.2 describes the process for installing VMS2.0 on-premises.

Section 3.3 describes how to set up the RTSP streaming services (both server and streams) on-premises.

Section 4.1 describes how to run VMSS2.0 pipelines using command line (both for on-premises setup and when using the VMAccel command line).

Section 4.2 describes the details of example pipelines.

Section 5.1 describes the configurations that are possible with Aupera Node Toolkit at the graph (i.e., pipeline) level.

Section 5.2 describes the configurations that are possible with Aupera Node Toolkit at the node level.

Section 5.3 lists the nodes that are currently available in Aupera Node Toolkit.

**NOTE:**

If you are using VMAccel, then you should read section 2. If you're interested in using the command line (on VMAccel) or understanding more details about the provided pipeline examples, you can look at section 4.

If you are interested in an on-premises setup (i.e., setting up VMSS2.0 on your own machine hosting one or more VCK5000 cards), you need to read section 3.



be solved using a tracker but, in this example, a back-edge is used to send the output fps of the video encoder to the box detector. This way, the box detector can notice whether the output fps of the video encoder has fallen (or there is a backlog of frames to be encoded) and can automatically increase the detection interval (i.e., how often the box detector is run). You can also see that the detection interval of the box detector is communicated to the box visualizer node in real-time.

Below, you can see the content of the ptxt file that describes the pipeline shown in Figure 1.1. As you can see, the box detector node will take the type of the model to run (ex. YoloV3, SSD, Refinedet, etc.) and the name of the specific kernel as input parameters. As such, this node can run any box detector model. To run your own model, all you need to do is place the compiled model along with its runtime prototxt config file (for AMD/Xilinx Model Zoo models, you can find this file provided along with the xmodel, please refer to an example provided [here](#)) under the directory `/usr/share/vitis_ai_library/models` in a folder matching the kernel name inside the AVAS docker. Detailed information about how to use the AVAS will be introduced later.

```
control_port: 51881
input_stream: "inStream1"
output_stream: "outStream1"

node {
  name: "stream_demux"
  calculator: "stream_demux"
  input_stream: "inStream1"
  output_stream: "packetstream1"
  side_node_name: "decode"
  side_node_name: "crowd_flow"
  output_side_packet: "stream_info:stream_info"
  node_options: {
    [type.googleapis.com/gvis.StreamMuxOptions]: {
      demux: {
        rtsp_transport: "tcp"
        iframe_extract: false
        auto_reconnect: true
      }
    }
  }
}

node {
```



```
name: "video decode"
calculator: "x86_dec"
input_stream: "packetstream1"
output_stream: "imgStream1080p"
side_node_name: "demux"
input_side_packet: "stream_info:stream_info"
node_options: {
  [type.googleapis.com/gvis.VideoCodecOptions]: {
    dec: {
      name: "x86_dec_h2645"
      ow: 1920
      oh: 1080
      opixfmt: "BGR24"
      queue_size: 10000
      low_latency: false
    }
  }
}

node {
  name: "box detector"
  calculator: "box_detector"
  input_stream: "imgStream1080p"
  output_stream: "detectionsStream"
  output_stream: "imgStream1080p_detOut"
  side_node_name: "tracker"
  side_node_name: "crowd_flow"
  output_side_packet: "detect_interval:detect_interval"
  stream_sync_mode: 1
  stream_sync_maxwait_ms: 60
  input_stream: "output_fps:output_fps"
  input_stream_info: {
    tag_index: "output_fps"
    back_edge: true
  }
  node_options: {
    [type.googleapis.com/gvis.BoxDetectorOptions]: {
      detect_interval: 5
      detector_type: "SSD"
    }
  }
}
```

```
    kernel_name: "RESNET18SSD_ITER90000_PRIVATE_FINAL501IMAGES
_ADDED_07JUNE2021_CROWD_FLOW_PERSON_HEAD"
    need_preprocess: true
    log_performance: true
    run_on_letterboxed_img: false
    label_confidence: {
      label: 2
      confidence: 0.5
    }
    inter_class_nms: {
      labels: 2
      threshold: 0.5
    }
  }
}

node {
  name: "box visualizer"
  calculator: "box_visualizer"
  input_stream: "detectionsStream"
  input_stream: "imgStream1080p_detOut"
  output_stream: "imgStream1080p_aplOut"
  side_node_name: "detector"
  input_side_packet: "detect_interval:detect_interval"
  stream_sync_mode: 1
  stream_sync_maxwait_ms: 60
}

node {
  name: "video encode"
  calculator: "x86_enc"
  input_stream: "imgStream1080p_aplOut"
  output_stream: "packetStream2"
  output_stream: "output_fps:output_fps"
  node_options: {
    [type.googleapis.com/gvis.VideoCodecOptions]: {
      enc: {
        name: "x86_enc_h264"
        w: 0

```

```
        h: 0
        fps: 0
      }
    }
  }
  side_node_name: "vfilter_node"
  side_node_name: "mux_node"
}

node {
  name: "stream_mux"
  calculator: "stream_mux"
  input_stream: "packetStream2"
  output_stream: "outStream1"
  node_options: {
    [type.googleapis.com/gvis.StreamMuxOptions]: {
      mux: {
        rtsp_transport: "tcp"
        auto_reconnect: true
      }
    }
  }
  side_node_name: "encode_node"
}
```

## 2 RUNNING VMSS2.0 ON VMACCEL

In this section, we will introduce the steps to sign-up for the VMACcel demo account, access the Aupera VMSS2.0 instance, launch custom RTSP streams for tasks, and run Aupera VMSS2.0 pipelines through both the Aupera Video AI Client (AVAC) and Aupera Video AI Server (AVAS) with detailed examples, including crowd flow pipeline and custom pipelines.

### 2.1 Launching Aupera VMSS2.0 instance on VCK5000

Please sign up for a demo account at: <https://www.vmaccel.com/vmssdemo>

After completing the sign-up form, you will receive an email with your demo credentials. Please follow the instructions in the email to log into VMACcel.

**NOTE:** The trial accounts allow 5 hours of free evaluation of VMSS2.0. The trial accounts are currently configured to automatically delete any instances when a user logs out. You may use a total of 5 hours of runtime, and this could be extended over several days. Your account will be locked once you have depleted 5 hours of runtime.

For each user, a VMACcel instance will be automatically launched. Once you login, under *Project-> Compute* you should see your instance by selecting “*Instances*” in the left-hand sidebar. You should be able to see the instance that was just created for you being spawned as shown in Figure 2.1.

Instance ID	Instance Name	Image Name	IP Address	Flavor	Key Pair	Status	Availability Zone	Task	Power State	Age	Actions
	Aupera VMSS2.0 Demo	Aupera Technologies VMSS2.0	184.105.10.122	VCK5000-PQ-1 (80.64.128)	default	Active	us-east-1	None	Running	35 minutes	Create Snapshot

**Figure 2.1. VMACcel instances main page**

After some time, the status of the instance will change to Active. At this point, the installation of the VMSS2.0 server and the client on the instance begin. Please allow about 3 minutes for this process to finish after you see the status has changed to Active.

**NOTE 1:** To run VMSS2.0 pipelines, you can either use Aupera’s VMSS2.0 Web Client (as described in section 2.2) or access the VMSS.2.0 server (as described in section 2.3) using the command line.

**NOTE 2:** To facilitate testing, the VMAccel instance will automatically start three RTSP streams:


**rtsp://<vmaccel\_instance\_ip\_address>:8554/retail**  
**rtsp://<vmaccel\_instance\_ip\_address>:8554/car**  
**rtsp://<vmaccel\_instance\_ip\_address>:8554/crowd**

**vmaccel\_instance\_ip\_address** is the IP address that is shown in the image above under IP Address when you are in *Project->Compute->Instances*. The first stream contains a crowded scene of people passing by and is the most useful for testing head, person, and other human related detections. We use this video for benchmarking our crowd applications. The second stream contains objects usually encountered in a retail scenario. We use this stream for throughput benchmarking.

Additionally, AVAC, the VMSS2.0 Web Client, can connect to any RTSP streams that are broadcast on open ports.

## 2.2 Using VMSS2.0 Web Client

After launching an Aupera VMSS2.0 instance on VMAccel, you can access the web client by copying the IP address of your instance into your browser on your local machine; and adding the port 3004. For example, in the screenshot below, the IP address of the instance is 184.105.10.164 which means that the web client can be accessed by typing <http://184.105.10.164:3004/> in your browser.



**Figure 2.2. VMAccel instances page with instance IP address highlighted**

**NOTE:** Since the relevant ports of your VMAccel instance are open to the public, you do not need to use the browser of the VMAccel instance (accessible through VNC) to launch the Web Client. You can use the browser on any machine with an internet connection.

### 2.2.1 Add Video Streams to Access Applications

- Click **Add Stream** to add at least one video stream to access the Application functions.




Figure 2.3. Aupera web application page

B. Enter a **Name** (any arbitrary name can be used) and **URL** (**S/N** is not required). **Make sure that RTSP URL is correct.** You can click the vertical ellipsis (three dots) icon on the added video stream to access the video stream configuration shown in Figure 2.4.

The image shows a dialog box titled "Add Video Stream" with a dark blue header. In the top right corner of the header are the words "Help", an information icon (i), and a close icon (X). The dialog contains three input fields: "Stream Name \*" with the value "CF Camera-1", "Stream URL \*" with the value "rtsp://<ip\_address>:8554/crowd", and "S/N" which is empty. At the bottom right, there are two buttons: a green "Save" button and a red "Cancel" button.

Figure 2.4. Aupera web application page – add video stream

**NOTE 1:** You can use either your own publicly available RTSP stream (perhaps the one you launched using the instructions in Section 2.2); or it can be one of the three RTSP streams that automatically started up when you launched your VMAccel instance.

For the latter you can use one of the following addresses:

rtsp://<vmaccel\_instance\_ip\_address>:8554/crowd

rtsp://<vmaccel\_instance\_ip\_address>:8554/retail

rtsp://<vmaccel\_instance\_ip\_address>:8554/car

Just make sure to replace the **vmaccel\_instance\_ip\_address** with the IP address of the VMAccel instance you just launched. You can find this IP address by clicking on the left-hand sidebar select “Instances” you can see the instance you just created being spawned as shown in Figure 2.5.

Stash To Create Aupera Instance

adam2.vmaccel.com/cloudboard/projects/instances/

Instances - VMACcel cloud

VMACCEL

asupera - asupera\_shared

Project

API Access

Compute

Overview

Editing

Instances

Displaying 4 items

Images

Key Pairs

Server Groups

Volumes

Container Infra

Network

Orchestration

DNS

Object Store

Share

Identity

Total Month Bill: 0.00 \$

Running Instances: 3

Uptime Total: 6.83 hours

Project / Compute / Instances

Instances

Instance ID:  Filter [Launch Instance](#) [Delete Instance](#) [More Actions](#)

<input type="checkbox"/>	Instance Name	Image Name	IP Address	Flavor	Key Pair	Status	Availability Zone	Task	Power State	Age	Actions	
<input type="checkbox"/>	my_instance	-	184.195.10.154	Not available	holleyPat	Build	us-east-1	None	Spawning	No State	0 minutes	<a href="#">Associate Floating IP</a>
<input type="checkbox"/>	Aupera Release 1.0.0	Aupera VCK5000	184.195.10.134	VCK5000-PQ.1 (80.64.128)	-	Active	us-east-1	None	Running	2 minutes	3 minutes	<a href="#">Create Snapshot</a>
<input type="checkbox"/>	asupera_release_1.0.0	-	172.16.1.251, 184.195.10.101	VCK5000-PQ.1 (80.64.128)	asupera_release_1.0.0	Shelved Offloaded	us-east-1	None	Shut Down	2 weeks, 5 days	1 day	<a href="#">Reconfigure Floating IP</a>
<input type="checkbox"/>	vmaccel_services	-	172.16.1.205, 184.195.10.252	m1.large	vmaccel_mac	Active	us-east-1	None	Running	4 weeks, 1 day	1 day	<a href="#">Create Snapshot</a>


Figure 2.5. VMAccel instances page – preparing a new instance

Again, the first stream shows a scene with people (used for crowd, person, and person attributed applications) while the second stream shows a scene with retail objects.


**NOTE 2:** If you need help in this step, click **Help** button in Figure 2.4 for more details about each input field and the next steps.

## 2.2.2 Running Aupera’s Crowd Flow Application

A. Click **AI Tasks Hub**, then click **Add New Task** button, then there will be a drop down to select a video stream




**Figure 2.6. Aupera web application page – AI Tasks Hub Page**



**Figure 2.7 Aupera web application page – AI Tasks Hub Page, Add New Task button clicked**


B. After selecting a Video Stream, another drop down will appear to select an application. Select Crowd Flow to open Crowd Flow application set up controls.





**Figure 2.8 Aupera web application page – AI Tasks Hub Page, Camera Selected**

C. After selecting Crowd Flow, another dropdown will appear to select an AI Host. Only AI hosts supporting the application selected in Application dropdown (see point above) will be displayed in this dropdown. Most of the time the Web Application will have a default AI host from the beginning. More AI Hosts may be added on the AI Hosts page. (For more information on AI Hosts page, please go to **2.2.5 AI Hosts**)



**Figure 2.9 Aupera web application page – AI Tasks Hub Page, AI Host Selected**

D. After Stream, Application, and AI Hosts are selected, the Crowd Flow Task Setup window will appear. (This is the right panel of the AI Tasks page extended,

collapsing this window by clicking **Task List** or **cancel** button will return to the previous page)





Figure 2.10. Aupera web application page – crowd flow task creation

E. You need to draw a line to indicate a border for people crossing. When a person's head crosses the line, IN/OUT count will reflect this event. These border lines may consist of up to a maximum of 14 segments, a less segmented line provides more accurate results. In and Out directions are determined by the way a line was drawn. If line is drawn from left to right, Movement from top to bottom will be registered as "IN", bottom to top - "OUT".

1. To start drawing, click the **Draw Line** button, the cursor will change to a cross.
2. **Left-click** and **hold the mouse button** on the place where you would like to start the line.
3. Drag the Line to the place where you want to finish the first segment, then release the mouse button.
4. Move a mouse to the end of the next segment to complete it.
5. To finish drawing, click the **Right mouse button**, unfinished segment will be deleted.

\* To see an animation of how this is done, click the help button beside **Draw** button

After the Line is drawn, “Draw Line” will change to “Redraw Line”. Click button if you want to delete the Line drawn and start drawing from the beginning. It is recommended to draw U shaped lines as shown in Figure 2.11 to capture people who may move parallel to the line and around it.




**Figure 2.11. Aupera web application page – crowd flow task lines drawing example**

F. Changing Basic Parameters is not required to start the task, you can keep default values.

1. **Direction** – Count people going “In”, “Out” (“Entering” / “Exiting”) or both directions
2. **Start/Stop Time** – counting will be started and stopped at the given time every day;
3. It is recommended to set **Sensitivity** to the default value of 0.05;


G. Advanced Parameters can significantly affect the results for a particular task, it is recommended to not change those until recommended by Aupera.



Parameter	Value
Debug Mode	Disable
Report Interval (s)	5
Head Confidence Threshold	0.5
Detect Interval (s)	5
Max Keep Alive	15
Min Hits	1
Affinity Threshold	0.008
Max Cluster Size	100
Min Person Area	200


**Figure 2.12. Aupera web application page – crowd flow task advanced AI parameters**

H. To start the task, click the **Submit** button. After that, a pop-up message will notify you that the task was successfully launched.




**Figure 2.13. Aupera web application page – success notification**

I. If the pop-up message reports an error, try launching the task with default parameters or check the settings.



**Figure 2.14. Aupera web application page – error notification**

J. If the task was launched, the task will appear in the task table on the left side of the screen



**Figure 2.15. Aupera web application page – crowd flow task control**

K. Select a task in task list or click **control** button on the row of the task to show the Crowd Flow Control on the right side of the screen.




Figure 2.16. Aupera web application page – crowd flow task control

L. To view results, click the **result** button on the specific task row on the table. The right panel will load the result of the specific task selected.




Figure 2.17. Aupera web application page – crowd flow task result

M. To visualize the AI pipeline of the task, click the **Open Visualizer Tool** Button at the bottom of the controls.




Figure 2.18. Aupera web application page – crowd flow task visualizer tool

The Visualizer will open in a new tab. Then, the AI pipeline graph representing current Crowd Flowd task will appear.




Figure 2.19. Aupera web application page – crowd flow task AI pipeline graph

N. To update Crowd Flow task set up, click **Configure CF Task** button, then the Crowd Flow Task Setup window will appear. Any parameter of the running task

can be changed. See Figure 2.11 to see more details in Crowd Flow Task set up. After completing the changes to Crowd Flow Task setup, click **Update** button to save changes. Updating task does not reset result counters.




Figure 2.20. Aupera web application page – crowd flow Configure Crowd Flow Task Button




Figure 2.21. Aupera web application page – Configure Crowd Flow Task popup

O. To stop the task, click **Stop CF Task** button, then Stop Crowd Flow Task confirmation will notify that the current task will be stopped. To proceed deleting the task, click **OK** button. To undo stop task, click **Cancel** button.




Figure 2.22. Aupera web application page – crowd flow Stop Crowd Flow Task Button






Figure 2.23. Aupera web application page – crowd flow Stop Crowd Flow Task confirmation popup

### 2.2.3 Running Custom Pipelines

A. Click **Add New Task** button, select a video stream from the drop down, and in **Select Application Type** drop down, select Custom Pipeline




Figure 2.24 Aupera web application page – AI Tasks Hub Page, Video Stream Selected

B. After Stream, Application (Custom Pipeline) and AI Hosts are selected, Custom Pipeline AI Editor will appear. (This is the right panel of the AI Tasks page extended, collapsing this window by clicking **Task List** or **cancel** button will return to the previous page) In the Editor you can type a PBTEXT configuration or **Import**

**From File** it from a file by clicking the corresponding button. You could also click **Download PBTXT** to save content of the editor.






Figure 2.25. Aupera web application page – custom pipeline task AI editor

C. You can also insert a node from **Insert Node** button. Click on the input field where you want the node to be inserted, then select a node to insert from the dropdown.




**Figure 2.26. Aupera web application page – custom pipeline task AI editor Insert Node selected**

D. You can also try Example Pipelines from **Example Pipeline** button. When an Example Pipeline is selected from the dropdown, the Input will be entirely replaced with the example pipeline



**Figure 2.27. Aupera web application page – custom pipeline task AI editor Example Pipeline selected**

E. Select **Model Zoo** button to look at the available models. Models can be filtered by Vendor, Category, and Type. To insert wanted model, select a model, then choose Pipeline PBTXT or Throughput PBTXT (if available). After choosing a model that is compatible with the AI host selected (for more information about AI host, go to 2.2.5 AI Hosts Page), the Model Zoo Selector popup will automatically close, and the input will be entirely replaced with the model pbtxt selected.



Application	Model Name	Category	Vendor	Hardware Engine	Hardware Type	Float Accuracy	Quantized Accuracy	Input Size	OPS
person-head	cf_SSD-RESNET18_PERSON-HEAD-SHUIUN_960_540_0.6.3G_2.0	detection	Aupera	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.8037	0.6323	960x540	6.3G
retail	dk_fmy-yolov3_416_416_5.46G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.9739	0.9650	416x416	5.46G
general	dk_yolov2_voc_448_448_34G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.7845	0.7740	448x448	34G
general	dk_yolov2_voc_448_448_54G_11.56G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.7700	0.7610	448x448	11.56G
general	dk_yolov2_voc_448_448_9.71.3.84G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.7670	0.7540	448x448	9.86G
general	dk_yolov2_voc_448_448_7.7.7.83G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.7576	0.7500	448x448	7.82G
general	dk_yolov3_voc_416_416_65.42G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.8040	0.8130	416x416	65.42G
sdas	dk_yolov3_ssd_384_384_53.7G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.9058	0.4910	384x312	53.7G
sdas	dk_yolov2_ptycapex_356_512_0.9.5.46G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.5520	0.5300	256x12	5.46G
general	tf_yolov3_voc_416_416_65.63G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.7846	0.7729	416x416	65.63G
general	cf_refinedet_coco_360_480_123G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.6928	0.7042	360x480	123G
general	cf_refinedet_coco_360_480_0.8.25G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.6794	0.6790	360x480	25G
general	cf_refinedet_coco_360_480_0.52.10.19G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.6409	0.6407	360x480	10.19G
general	cf_refinedet_coco_360_480_0.96.5.08G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.6120	0.6112	360x480	5.08G
general	tf_refinedet_VOC_320_320_81.9G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.8015	0.7999	320x320	81.9G
sdas	cf_nucleus_dsd_360_480_0.99.8.3G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.4307	0.4300	360x480	6.3G

Figure 2.28. Aupera web application page – custom pipeline task AI editor Model Zoo Selected



Application	Model Name	Category	Vendor	Hardware Engine	Hardware Type	Float Accuracy	Quantized Accuracy	Input Size	OPS
person-head	cf_SSD-RESNET18_PERSON-HEAD-SHUIUN_960_540_0.6.3G_2.0	detection	Aupera	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.8037	0.6323	960x540	6.3G

Figure 2.29. Aupera web application page – custom pipeline task AI editor Model Zoo Selector, filter by Vendor “Aupera”

Application	Model Name	Category	Hardware Type	Float Accuracy	Quantized Accuracy	Input Size	OPS
general	cf_resnet18_imagenet_224_224_3.65G_2.0	classification	xilinx_vck5000_gen3x16_xdma_base_1	0.6844/0.8864	0.6699/0.8826	224*224	3.65G
general	cf_resnet50_imagenet_224_224_7.7G_2.0	classification	xilinx_vck5000_gen3x16_xdma_base_1	0.7444/0.9185	0.7335/0.9130	224*224	7.7G
general	cf_inceptionv1_imagenet_224_224_3.16G_2.0	classification	xilinx_vck5000_gen3x16_xdma_base_1	0.7030/0.8971	0.6964/0.8942	224*224	3.16G
general	pt_resnet50_imagenet_224_224_4.1G_2.0	classification	xilinx_vck5000_gen3x16_xdma_base_1	0.7610/0.9290	0.7603/0.9280	224*224	4.1G
general	tf2_resnet50_imagenet_224_224_7.76G_2.0	classification	xilinx_vck5000_gen3x16_xdma_base_1	0.7513/0.9220	0.7437/0.9214	224*224	7.76G
general	tf_inceptionv1_imagenet_224_224_3G_2.0	classification	xilinx_vck5000_gen3x16_xdma_base_1	0.6976/0.8963	0.6786/0.8852	224*224	3.0G
general	tf_milperf_resnet50_imagenet_224_224_8.19G_2.0	classification	xilinx_vck5000_gen3x16_xdma_base_1	0.7652/0.9301	0.7536/0.9264	224*224	8.19G
general	tf_resnetv1_101_imagenet_224_224_14.4G_2.0	classification	xilinx_vck5000_gen3x16_xdma_base_1	0.7640/0.9289	0.7414/0.9176	224*224	14.4G
general	tf_resnetv1_152_imagenet_224_224_21.83G_2.0	classification	xilinx_vck5000_gen3x16_xdma_base_1	0.7681/0.9317	0.7464/0.9220	224*224	21.83G
general	tf_resnetv1_50_imagenet_224_224_6.97G_2.0	classification	xilinx_vck5000_gen3x16_xdma_base_1	0.7520/0.9219	0.7411/0.9167	224*224	6.97G

Figure 2.30. Aupera web application page – custom pipeline task AI editor Model Zoo Selector, filter by Category “classification”

Application	Model Name	Category	Vendor	Hardware Engine	Hardware Type	Float Accuracy	Quantized Accuracy	Input Size	OPS
person-head	cf SSD-RESNET18_PERSON-HEAD-SHUIUN_960_540_0_6.3G_2.0	detection	Aupera	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.8037	0.6323	960x540	6.3G
retail	dk_tiny_yolov3_416_416_5.46G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.9739	0.9650	416x416	5.46G
general	dk_yolov2_voc_448_448_34G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.7845	0.7740	448x448	34G
general	dk_yolov2_voc_448_448_0.66_11.56G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.7700	0.7610	448x448	11.56G
general	dk_yolov2_voc_448_448_0.71_9.86G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.7670	0.7540	448x448	9.86G
general	dk_yolov2_voc_448_448_0.77_7.82G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.7576	0.7500	448x448	7.82G
general	dk_yolov3_voc_416_416_65.42G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.8240	0.8130	416x416	65.42G
adas	dk_yolov3_bdd_288_512_53.7G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.5058	0.4910	288x512	53.7G
adas	dk_yolov3_cityscapes_256_512_0.9_5.46G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.5520	0.5300	256x512	5.46G
general	tf_yolov3_voc_416_416_65.63G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.7846	0.7729	416x416	65.63G
general	cf_refinedet_coco_360_480_123G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.6928	0.7042	360x480	123G
general	cf_refinedet_coco_360_480_0.8_25G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.6794	0.6790	360x480	25G
general	cf_refinedet_coco_360_480_0.92_10.10G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.6489	0.6487	360x480	10.10G
general	cf_refinedet_coco_360_480_0.96_5.08G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.6120	0.6112	360x480	5.08G
general	tf_refinedet_VOC_320_320_81.9G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.8015	0.7999	320x320	81.9G
adas	cf_ssddas_bdd_360_480_0.95_6.3G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1	0.4207	0.4200	360x480	6.3G

Figure 2.31. Aupera web application page – custom pipeline task AI editor Model Zoo Selector, filter by hardware type.

Model Zoo Selector					
Select Vendor		Select Category			
Application	Model Name	Category	Vendor	Hardware Engine	Hardware Type
person-head	cf_SSD-RESNET18_PERSON-HEAD-SHIUN_960_540_0_6.3G_2.0	detection	Aupera	8pe	xilinx_vck5000_gen3x16_xdma_base_1
retail	dk_tiny-yolov3_416_416_5.46G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1
general	dk_yolov2_voc_448_448_34G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1
general	dk_yolov2_voc_448_448_0.66_11.56G_2.0	Pipeline PBTXT Throughput PBTXT		8pe	xilinx_vck5000_gen3x16_xdma_base_1
general	dk_yolov2_voc_448_448_0.71_9.86G_2.0			8pe	xilinx_vck5000_gen3x16_xdma_base_1
general	dk_yolov2_voc_448_448_0.77_7.82G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1
general	dk_yolov3_voc_416_416_65.42G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1
adas	dk_yolov3_bdd_288_512_53.7G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1
adas	dk_yolov3_cityscapes_256_512_0.9_5.46G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1
general	tf_yolov3_voc_416_416_65.63G_2.0	detection	Xilinx	8pe	xilinx_vck5000_gen3x16_xdma_base_1


Figure 2.32. Aupera web application page – custom pipeline task AI editor Model Zoo Selector, model selected

**NOTE:** Before using Insert Node/Example Pipelines/Model Zoo, make sure that the machine has internet access.

F. Before starting the task, please enter *Output RTSP URL* (this value needs to follow a specific format of **rtsp://<vmaccel\_instance\_ip\_address>:8554/<user\_specified\_name>**). Click Submit to start the Custom Pipeline task.


**NOTE:** <user\_specified\_name> can be any arbitrary name that the user chooses.

G. After submitting the task, if there are missing model, there will be popup displayed informing which model is missing. Click **OK** to download model, or **Cancel** to download later.



**Figure 2.33. Aupera web application page – Custom Pipeline Submit Task download model popup.**

Or, if all models are validated on current AI host, the popup will give the option to start custom pipeline task immediately. Click **OK** to start task or **Cancel** to start later.



**Figure 2.34. Aupera web application page – Custom Pipeline Submit Task confirm starting task popup.**

If Task cannot run due to unavailable control port, The following popup will show. In this case, click **OK** to close popup, go to editor and change the input control port to an available control port and **Submit** the task again.




Figure 2.35. Aupera web application page – task launch failed notification

H. If the task was started, but then crashed after some time, message about that will be displayed









Figure 2.36. Aupera web application page – task crashed notification

I. When the task is submitted, it will appear in the task list. Depending on whether the custom pipeline task's current status, status will show different icon.

Table 1.1. Aupera web application page – Custom pipeline tasks' status icon

Icons	Definition	Instructions
	Model missing	To download missing model, select entry from table, click <b>Open AI Editor</b> button. Click <b>OK</b> on popup notification on downloading model.
	Model downloading	Wait until model are successfully downloaded to run task.



	Model ready	Model are downloaded and task is ready to run. Select entry from table, click <b>Open AI Editor</b> button. Click <b>OK</b> on popup notification on starting task.
	Task is running	Task is successfully running.
	Task failed	Task failed. Select entry from table, click <b>Open AI Editor</b> button. Click <b>Stop Task</b> button. You can restart task following start custom pipeline task instruction again.

J. When the task row in task list or the **control** button on the row is clicked, the right side of the screen will show the Custom Pipeline control component.




Figure 2.37. Aupera web application page – custom pipeline task control

K. If AI Editor is opened for a running task, current PBTEXT configuration will be displayed in the editor field. However, task update is not supported now, so please stop and start the task again in case any changes in PBTEXT are required.




Figure 2.38. Aupera web application page – custom pipeline task pbtxt example

L. To see the Custom Pipeline task results (output video), click **result** button on the specific task in task table.




Figure 2.39. Aupera web application page – custom pipeline task result

**NOTE:** After the Custom Pipeline Task started, it may take up to a few seconds before an output video stream starts. “Video failed to load” error may occur when checking custom pipeline result right after the task is started. Wait a few seconds and click the refresh button to try displaying the output video again.




Figure 2.40. Aupera web application page – custom pipeline task result, “Video failed to load” error





Figure 2.41. Aupera web application page – custom pipeline task result page (output video not yet available)

**NOTE:** Refresh the page if Custom Pipeline task result failed to load after running the task for a long time.

M. To stop the task, click Stop Task in the Custom Pipeline control component.


## 2.2.4 Using Video Streams to Add New Stream, play videos, or change snapshots

A. Click **Video Streams**, then click **Add New Stream** button, then popup will appear shown in Figure 2.4.




**Figure 2.42 Aupera web application page – Video Streams Page**

B. To play the video, select a Stream from Video Stream List. Video playback will start immediately. If another video stream is clicked, video playback will switch to this video stream.



**Figure 2.43 Aupera web application page – Video Stream Page, video stream selected**


C. The video can also be played and stopped by clicking the stop and play button located in the bottom right corner of the video play.



**Figure 2.44 Aupera web application page – Video Stream Page, stopped button clicked**

**NOTE:** Video player should start playing shortly after the play button is clicked. If the video player does not start playing after clicking the play button for 10 – 15 seconds, click the stop button and play button again to restart the video play.


D. Video stream preview will be taken automatically in several seconds after the stream is played for the first time. To change the snapshot, click the Camera Button beside the play button while the video is playing



**Figure 2.45 Aupera web application page – Video Stream Page, snapshot taken**

Click **OK** button to update the snapshot or **Cancel** button to cancel updating the snapshot.


E. To view four video streams in the same screen, click the four rectangle icon located on the top right corner of the screen. To play video on a specific Video Player, choose a video frame by clicking directly on the video frame and select a video to play from Video Stream List, or use the Play button at the bottom right corner of each video frame to play or stop video play.



**Figure 2.46 Aupera web application page – Video Stream Page, 4 video frames view**


## 2.2.5 AI Hosts Page

A. User will be given a default AI Host when first starting the web application.




**Figure 2.47 Aupera web application page – AI Host Page**

B. Information about the AI host can be checked by clicking on the entry of the AI host in AI host list.



**Figure 2.48 Aupera web application page – AI Host Page, AI Host Info**


C. To Add a new AI host, click on **Add New AI Host** button and a popup will appear for user to check the AI host url to be added



**Figure 2.49 Aupera web application page – AI Host Page, Add New AI Host**

**NOTE:** If you need help in this step, click **Help** button in Figure 2.49 for more details about each input field and the next steps.

D. Enter a valid AI host name (name cannot be “default”) and URL (AI host URL should start with “http”), then click **Check AI Host** (To successfully save AI host, AI host name and URL must be verified through check AI host information)




**Figure 2.50 Aupera web application page – Host Page, Add New Host – host URL checked**

During Check AI Host, AI host URL can be modified at any time. Then user can click **Check AI Host** button again if modification of URL is needed.

After clicking the **Submit** button, the new added AI host will appear in the AI Host list and ready to use throughout the entire web application.

E. To delete an AI host, click on the **X** button on the specific AI host that are intended to be deleted on the AI host list. Then select **OK** on the delete AI host confirmation popup



**Figure 2.51 Aupera web application page – Host Page, Delete Host confirmation popup**

**NOTE:** If there is no AI Host added to the web application, the user will not be able to access any task related functions. Therefore, users will not be able to access AI Tasks tab if there is no AI host added. To access and start tasks, make sure there is at least one AI host added, otherwise the AI Tasks tab will be blocked.





Figure 2.52 Aupera web application page – AI Host Page, No AI Host added

2.2.6 Useful tools

A. **Filter** located at the top of the task list can filter items in task list. To use **Filter**, simply type in the input field or select an item by clicking the input field or the arrow button to filter the task list item by Video Stream, AI Application, Task Status, or AI Hosts




Figure 2.53 Aupera web application page – AI Tasks Hub, filter by Video Stream




Figure 2.54 Aupera web application page – AI Tasks Hub, filter by AI Application




Figure 2.55 Aupera web application page – AI Tasks Hub, filter by AI Host

B. Arrow buttons in the middle of the AI Tasks Hub page help adjust the ratio of the screen for a more convenient and customized view. Right arrow can be clicked to extend the table view. Left arrow can be clicked to extend what exists on the right side of the screen. When one view is extended, a bar will appear to help collapse the screen.




Figure 2.56 Aupera web application page – AI Tasks Hub view on smaller screen




Figure 2.57 Aupera web application page – AI Tasks Hub, table(left) view extended




Figure 2.58 Aupera web application page – AI Tasks Hub, right view extended

## 2.3 Using VMSS2.0 Server (via command line)

To use AVAS, the VMSS2.0 Server, you need to launch a VMACcel terminal and go into the docker for VMSS2.0 Server. Once there, you can run any pipelines directly from the command line.

### 2.3.1 VMSS2.0 Server Docker

A. In the left-hand sidebar select “**Instances**”. Then, click on the name of your instance.




Figure 2.59. VMACcel instances page – instance selection

B. Select the **Console** tab as Figure 2.28 shows.




Figure 2.60. VMAccel instances page – instance console

C. Once the VNC window opens click on Connect as Figure 2.29 shows.




Figure 2.61. VMAccel console page – instance console connection

D. Inside the VMAccel VNC window, click on the Terminal icon to open a command line shell terminal.




Figure 2.62. VMAccel console page – terminal emulator highlighted

E. From the terminal, you can enter the VMSS2.0 server's docker by running the command:

```
docker container exec -it aupera_server bash
```




Figure 2.63. VMAccel console page – accessing VMSS2.0 server's docker

F. Once inside the docker, you will need to setup the environment (xbutil and vitis) by running the command below from any directory.

```
source set_env.sh
```




Figure 2.64. VMAccel console page – setting up software environment

At this point, the docker is ready to be used and you can proceed to section 4.

**NOTE:** Usually, you can kill the VMSS2.0 tasks (launched via the command line) by pressing CTL + C on your keyboard. For the throughput measurements tasks, you might

need to press CTL + C a few times and / or use CTL + | combination to kill all the threads.

## 2.4 Launching Your Own RTSP Streams

You can run VMSS2.0 pipelines either on RTSP streams (including the one from your IP camera) or on videos. If you are using the RTSP streams provided (mentioned above under NOTE 2 in Section 2.1), you can skip this section and move on to section 2.3.

This section focuses on helping the user to broadcast their test videos via an RTSP server. Before continuing, please make sure FFMPEG is downloaded on your local machine and accessible via the command line. Visit the [FFMPEG download](#) page for further instructions.

For your video file residing on your local machine to be pushed into a RTSP server, you can follow the instructions below:

- A. You can publish a stream using

```
ffmpeg -re -stream_loop -1 -i file.ts -c copy -f rtsp  
rtsp://server_ip:8554/mystream
```

Where *file.ts* is your video file residing on your local machine and *server\_ip* is the IP address of your VMAccel instance.

**NOTE:** The key *mystream* (in *rtsp://server\_ip:8554/mystream* above) should be a unique string for each stream.

- B. You can then watch the stream using VLC (or any other video player) through **media/open network** stream option, by hitting *ctrl+n* or by using

```
vlc rtsp://server_ip:8554/mystream
```

You can download VLC from [here](#).

## 3 **RUNNING VMSS2.0 ON-PREMISES**

### 3.1 Prerequisites

A. machine with X86 processor running Ubuntu 18.04 and containing at least one VCK5000 board (along with PCIe x16) to host the VMSS 2.0 server. From now on, this machine will be referred to as the X86 host

B. machine to host the VMSS 2.0 client (web-application). This machine could run Linux, or Windows. Optionally, it could, also, be the same machine hosting the server.

C. docker version 20.10.8 or above installed. You can check this using

```
sudo docker --version
```

D. docker compose version v2.4.1 or above installed. You can check this using

```
sudo docker compose version
```

### 3.2 VMSS2.0 server (AVAS)

A. Load the docker using

```
sudo docker load -i VMSS2.0_AVAFx.x.x_AVASx.x.x_VCK5000-  
prod.tar.gz
```

B. Download VMSS2.0 server docker (VMSS2.0\_AVAF2.0.0\_AVAS2.0.0\_VCK5000-prod) and the docker\_run\_2.sh script from OneDrive and upload them onto the X86 host (the machine hosting the VCK5000 card)

C. Start the VMSS 2.0 server docker using the provided docker\_run\_2.sh script. By running

```
sudo ./docker_run_2.sh  
auperastor/video_ai_framework:VMSS2.0_AVAFx.x.x_AVASx.x.x_VCK500  
0-prod VMSS2.0_AVAFx.x.x_AVASx.x.x_VCK5000-prod
```

You might need to change the permissions of docker\_run\_2.sh before running it using

```
sudo chmod 7777 docker_run_2.sh
```

D. Please note that our VMSS2.0 server dockers are locked using device serial numbers. In order to use our docker, you will need to send us the serial number of the device that is intended to run the server. In turn, we will provided you with a public-private key pair. You will then need to place both the public key (e.x. pubkey.pem) and



the private key (e.x. key.json) in the **/opt/aupera/avas/etc/** folder of the docker before running the start.sh script.

E. If you're planning on only using the web-application to run tasks, you can run the docker in detached mode using

```
sudo docker exec -it VMSS2.0_AVAFx.x.x_AVASx.x.x_VCK5000-prod  
bash start.sh
```

F. To see the debugging screen you can use

```
sudo docker exec -it VMSS2.0_AVAFx.x.x_AVASx.x.x_VCK5000-prod  
bash start.sh debug
```

You can exit the debugging screen with **Ctrl+A D** to exit debug screen

G. If you're planning on using the command line server (instead of the web-application), instead of above two steps (steps 4 and 5), you can go inside the container using

```
sudo docker exec -ti container_name bash
```

And then start the server (listening to the client) by running **start.sh** in any directory (from inside the docker)

H. If you are not running the start.sh script (i.e., you're planning on just using the command line to run pipelines without using the client/ avas server), then you need to source the xbutil and Vitis environments by running the command:

```
source set_env.sh
```

The set\_env.sh script is on the path (located in **/opt/aupera/avas/etc/**) so it the command above can be ran from any locations inside the docker.

### 3.3 Setting up RTSP Streams

Inside the VMSS2.0 server's docker, you will find a folder called **/opt/aupera/avas/EasyDarwin** as shown in the screenshot below:

```
(base) root@general:/opt/aupera/avas/EasyDarwin# pwd  
/opt/aupera/avas/EasyDarwin  
(base) root@general:/opt/aupera/avas/EasyDarwin# ls  
crowd_flow_test.mp4  easydarwin  easydarwin.pid  easydarwin.xml  lunch_many_streams.sh  retail.mp4  start_streams.sh  
(base) root@general:/opt/aupera/avas/EasyDarwin#
```

Inside of this (EasyDarwin) folder, you will find two scripts:

A. If you run the command: “./start\_streams.sh” you will start the server and two streams. stream1 is a crowd video and stream2 is a retail video.

- If you run this script (in a separate shell) you will be able to run all the examples except throughput\_benchmarking\_using\_retail\_application.
- If you'd like to use rtsp run:

```
avaser -i input.pbt.txt -o output.pbt.txt using_rtsp...pbt.txt
```

- If you'd like to use video run:

```
avaser -i input.pbt.txt -o output.pbt.txt using_video.pbt.txt
```

- using both rtsp and video. You can see the output rtsp at:

```
rtsp://yourMachineIP:554/out1
```

(just replace yourMachineIP with the actual IP address of your machine)

B. The second script lunches many rtsp streams. This is to test the throughput\_benchmarking\_using\_retail\_application example.

- You can lunch the streams by running:

```
./lunch_many_streams.sh #ofStreams
```

- For example, to test 37 streams you should run:

```
./lunch_many_streams.sh 37
```

- To test 56 streams you should run:

```
./lunch_many_streams.sh 56
```

- If you are running the 37 examples with video output using the command

```
avaser -i input.pbt.txt -o output.pbt.txt -c  
config_withTracker_withVideoOut.pbt.txt
```

- Then you can watch the output video streams at:

```
rtsp://yourMachineIP:554/out1" through  
"rtsp://yourMachineIP:554/out37
```

(just replace yourMachineIP with the actual IP address of your machine)

- If you are running the 37 examples without video output, please make sure to use the empty.pbt.txt as output (passed by -o options). Basically, the command you would run would be:

```
avaser -i input.pbt.txt -o empty.pbt.txt -c  
config_noTracker_noVideoOut.pbt.txt
```

## 4 VMSS2.0 PIPELINES

### 4.1 Running VMSS2.0 Pipelines

Generally, to run a VMSS2.0 pipeline, you can run the command below from any directory inside of the VMSS 2.0 server docker. There are 3 ptxt files that are required to pass to *avaser*:

1. **Input:** comes after *-i* parameter and contains the same number of RTSP streams as the `input_streams` contained in your `pipeline.ptxt`.
2. **Output:** comes after *-o* parameters and contains the same number of rtsp streams (or file passes) as the `output_streams` contained in your `pipeline.ptxt`.
3. **Config:** comes after *-c* parameter and contains your pipeline definition (the list of nodes and connections).

Below as an example of what the command should look like:

```
avaser -i input.ptxt -o output.ptxt -c pipeline.ptxt
```

Below is an example of the content of an `input.ptxt` file:

```
input_urls: "rtsp://10.10.190.114:554/key1"  
input_urls: "rtsp://10.10.190.114:554/key2"  
input_urls: "rtsp://10.10.190.114:554/key3"
```

Below is an example of the content of an `output.ptxt` file:

```
output_urls: "rtsp://10.10.190.114:554/key4"  
output_urls: "rtsp://10.10.190.114:554/key5"  
output_urls: "/tmp/output_video_file.mp4"
```

**NOTE 1:** The `output.ptxt` file could be empty if there are no output streams.

**NOTE 2:** The `output.ptxt` file could contain file paths instead, in which case, the encoded video will be saved to disk instead of being sent to the RTSP streaming server.

### 4.2 Pipeline Examples

We have provided several examples of full pipelines [here](#). These are also included in the `aupera_server` docker in the `/opt/aupera/avas/examples` folder. You can navigate to this location using the following command:

```
cd /opt/aupera/avas/examples
```

In most of the example folders there are two sets of pipelines pbtxt files: one called **using\_rtsp...pbtxt** and another called **using\_video.pbtxt**.

If you'd like to try the example pipelines on the sample videos, then all you need to do is to go inside the sub-folder of a specific example (box\_detector, box\_detector\_classifier\_cascade, or apl\_crowd\_flow) and run the following command:

```
avaser -i input.pbtxt -o output.pbtxt -c using_video.pbtxt
```

If you'd like to try the example pipelines on the RTSP streams that are automatically started by your VMAccel instance, then all you need to do is go inside the sub-folder of a specific example and run:

```
avaser -i input.pbtxt -o output.pbtxt -c using_rtsp.pbtxt
```

The results of our examples will be broadcast in the IP address specified in the output.pbtxt file. In most cases, this is set to

```
output_urls: "rtsp://localhost:8554/out1"
```

which means that you can see the results by typing above RTSP URL into VLC; replacing "localhost" with the IP address of your VMAccel instance.

**NOTE 1:** If you'd like to run the pipelines on videos other than what we have provided, you will need to modify the "path" parameter in the video\_stream node. As shown in Figure 4.1 below:

```
node {
  name: "video_stream_node"
  calculator: "video_stream"
  input_stream: "inStream1"
  output_stream: "imgStream1080p"
  side_node_name: "crowd_flow"
  node_options: {
    [type.googleapis.com/gvis.VideoStreamOptions]: {
      path: "/opt/aupera/avas/examples/videos/C235-2021-04-21-13-13-04_first90S.mp4"
    }
  }
}
```

**Figure 4.1. Aupera video stream output path in pbtxt file**

**NOTE 2:** If you'd like to try our example pipelines on RTSP streams other than the ones launched by your VMAccel instance, then you will need to edit the input.pbtxt files to set the input\_rtsp parameter to the URL of your RTSP streams.

For example, if the input.pbtxt of the example you are using contains:

```
input_urls: "rtsp://10.10.100.100:8554/stream1"
```

And the IP address of your VMAccel instance is 99.99.999.999:554/mystream, then you should edit your input.pbt.txt to contain the following:

```
input_urls: "rtsp://99.99.999.999:554/mystream"
```

**NOTE 3:** To see the results of example pipeline on RTSP streams in other locations you will need to edit the output.pbt.txt file in each folder to point either to the IP address of your RTSP sever; or to a valid file path. For example, if you're inside the box\_detector example folder, and the IP address of the machine running your RTSP server is 10.10.100.100, then you will need to adjust the output.pbt.txt to contain:

```
output_urls: "rtsp://10.10.100.100:8554/someKey"
```

In above case, you can watch the pipeline results at the RTSP stream provided above. Alternatively, your output.pbt.txt could include line similar to:


```
output_urls: "/tmp/video_output.mp4"
```

In above case, the pipeline's results will be saved to disk in a file accessible via the path specified above.

**NOTE 4:** Usually, you can kill the VMSS2.0 tasks (launched via the command line) by pressing CTL + C on your keyboard. For the throughput measurements tasks, you might need to press CTL + C a few times and / or use CTL + | combination to kill all the threads.

The pipeline examples that are included with the correct release are as follows:


**A. box\_detector/using\_rtsp\_0output.pbt.txt**



**Figure 4.2. Aupera pipeline example with demux, decode, and detector nodes**

The pipeline in Figure 4.2 takes one input stream, runs a `box_detector` network on the decoded frames, visualizes the detections on the frames, and saves the frames to disk (there is no output video).

**B. `box_detector/using_rtsp_1output.pbtxt`**




**Figure 4.3. Aupera pipeline example with multiple nodes 1**

The pipeline in Figure 4.3 takes one input stream and one output stream. It runs a box\_detector network on the decoded frames and sends the detected bounding boxes and the frames to the box\_visualizer node. The box\_visualizer node, will visualize the detected bounding boxes on the frames and send them to video filter, video encoder, and mux nodes. The results are returned in an output rtsp stream or video file.

**C. apl\_crowd\_flow/using\_rtsp.pbtxt :**






**Figure 4.4. Aupera pipeline example with multiple nodes 2**

The pipeline in Figure 4.4 takes one input stream and one output stream. It runs a box\_detector (at some interval), which passes the detected bounding boxes and the frames to a box\_Tracker. The box\_tracker tracks the objects (even on frames where the detector has not been run) and sends the bounding boxes and the frames to our crowd\_flow application node. This node applies the crowd\_flow logic; visualizes the results; and passes the frames to the video filter, encode, and mux nodes. The results can be seen in the output rtsp stream or a video file.


#### **D. box\_detector\_classifier\_cascade/using\_rtsp.pbt.txt**



**Figure 4.5. Aupera pipeline example with two input and output streams**

The pipeline in Figure 4.5 takes two synchronized input streams and produces two output streams. It runs a box detector (at some interval). Then it passes the frames in-tandem with the detections to the classifier node. The classifier node then classifies the objects detected by the detector node. It passes the classifications, which sends the results of each stream to its corresponding box\_visualizer node. The box\_visualizer will overlay the detections and classifications on the frames and send the results to video filter, stream encode, and stream mux nodes to be displayed over RTSP stream.

#### E. box\_detector/using\_rtsp.pbtxt



**Figure 4.6. Aupera pipeline example with two input and output streams**

The pipeline in Figure 4.6 is very similar to example B (figure 4.3); except it runs two detection tasks in parallel. This pipeline takes two input streams and produces two output streams. On stream 1, it runs a box detector with crowd models (head detection); while, on stream 2, it runs a box detector with retail models. The detection results are then passed to corresponding box\_visualizer nodes. The box\_visualizer nodes will overlay the detections on the frames and send the results to video filter, stream encode, and stream mux nodes to be displayed over RTSP stream.

## F. Throughput measurement using retail application

Similar to VMSS1.0, we use the retail application as an example pipeline for throughput measurement. This application consists of running a TinyYoloV3 object detector along

with 3 resnet50 classification networks. All the networks are trained on the objects in the retail scenario. We also use the same retail.mp4 video as before (provided in the example\_videos folder). We maintain (and slightly exceed) the performance of VMSS1.0 by supporting 37 streams (with I-frame-extraction) without any trackers and with 56 streams when using a tracker. We have, however, dramatically improved the accuracy of the pipeline when a tracker is used compared to VMSS1.0.

If you look inside the **example\_pipelines/throughput\_benchmarking/37streams**, you will find 3 configurations:

- **config\_noTracker\_noVideoOut.pbtxt** is the official test configuration. To run this test, you must ensure that the output.pbtxt file is empty.
- **config\_withTracker\_noVideoOut.pbtxt** performs the same test except the tracker is used. Here, we use a cluster size of 5 (i.e. classify each track 5 times) to achieve higher accuracy.
- **config\_withTracker\_withVideoOut.pbtxt** can be used to watch the visualized results on the output stream. To run this config, you will need to use the provided output.pbtxt with the correct output stream paths. Please note that since video visualization is a computationally expensive operation, it is only allowed while running the tracker. Also please note that when I-frame-extraction is true, the output video stream can only be saved at 10fps (since the video has an I-frame every 3<sup>rd</sup> frame). You can set I-frame\_extraction to false, in order to run and save the video at 30fps but that would require reducing the total number of streams (since we are making the test 3 times harder by passing 3 times the number of frames to the pipeline).

Finally, inside **example\_pipelines/throughput\_benchmarking/56streams** we have provided a single config (**config\_withTracker\_noVideoOut.pbtxt**) which can be used to confirm that the framework can run the retail pipeline with 56 streams without any frame drops. You can increase the **classifications\_cluster\_size** parameter to achieve higher classification accuracy if needed. Although, in this example, even with a value of 1, the classification accuracy is not far lower than running without a tracker. Essentially, this parameter specifies how many times we run the classification on each track. For example, when a value of 5 is specified, for each track, we run the classifier 5 times, and use the most frequent (i.e., the mode) classification as the final result.

## 5 AUPERA NODE TOOLKIT

Aupera's Node Toolkit provides a collection of highly configurable nodes to help users build and launch their own pipelines as quickly as possible. Using VMSS2.0 users no longer have to write any code for tasks that are common to most CV pipelines such as demux, decode, preprocessing, running object detection and classifications, tracking, mux, and encoding. The rest of this section describes the configurations that all VMSS2.0 will support at the pipeline level, configurations that all VMSS2.0 nodes will accept, and a list of nodes currently provided in Aupera Node Toolkit.

### 5.1 Graph-level Configurations

Currently VMSS 2.0 allows for the following configurations at the graph level:

```
// collection of nodes that comprise the graph
repeated Node node

//(optional) total number of threads used to execute the graph,
if not provided each graph with an execute method will run in
its own thread
int32 num_threads

// (optional) default max queue size for each node data stream,
this can be overridden by individual nodes
int32 max_queue_size

// Names of the input streams for the graph. If using the
command line (as opposed to the VMSS 2.0 client), the order of
these streams must match the order of the stream URL(s) passed
to the server when executing the graph.
repeated string input_stream

// Names of the output streams for the graph. If using the
command line (as opposed to the VMSS 2.0 client), the order of
these streams must match the order of the stream URL(s) passed
to the server when executing the graph.
repeated string output_stream

// (optional) control port, may be used by the udp/tcp server to
communicate runtime control command send by VMSS 2.0 client
int32 control_port
```

## 5.2 Node-level Configurations

Currently VMSS 2.0 allows for the following configurations at the node level:

```
// (optional) the name of this node used for visualization
purposes
string name

// official name of the node. This needs to match the name the
node was registered with and the name of the calculator binary
string calculator

// names of the input streams to the node. These names must be
unique in the graph. Each name (i.e., input stream) also
requires either a graph level input stream or a node level
output stream with the same name. You can also use the name:tag
format to add a tag for display purposes
repeated string input_stream

// names of the output streams to the node. These names must be
unique in the graph. You can also use name:tag format to use a
tag for display purposes
repeated string output_stream

// (optional) synchronization mechanism applied to this node by
the framework. If not provided, the framework will use a default
value of 0
//The following synchronization modes are currently supported:
//0: no synchronization the execute method is called as soon as
any of the input streams of the node has a packet available
//1: synchronization using an incremental value (such as pts,
gts, or frame number)
//The framework will call the execute methods once all the
node's input streams have at least one packet available. The
framework will buffer the packets from the earlier streams while
waiting for the delayed streams
//2: sync with incremental value but with reuse of last element
//The initial behavior of this mode is similar to type 1, except
that for subsequent packets the framework will call the execute
```

```
method of the node as soon as any of the input streams has a
packet by cloning the last packet of the input streams
int32 stream_sync_mode

// (optional) maximum number of milliseconds that the framework
will on the next packets before forcing the output (i.e.,
breaking the synchronization promise). By default, this is set
to infinity.
int32 stream_sync_maxwait_ms

// (optional) maximum size of the input queue for this node,
this value is set per input stream. Once this value is reached,
the framework will no longer enqueue packets for the node until
the packets already in the pipeline are consumed (i.e., the
input queue size falls below this maximum threshold). This
parameter is set to 12 by default.
int32 queue_size

// (optional) list of the names of the nodes that this node
communicates with via side-packet communication. Both nodes must
have each other's names in their side_node_name list to be able
to communicate.
repeated string side_node_name

// (optional) the maximum size of the side packet message queue
for this node. Once this size is reached, the nodes trying to
enqueue messages for this node will receive an error message
until this node has consumed at least one of its messages. By
default, this parameter is set to infinity.
int32 max_side_queue_size

// maximum number of threads that this node is allowed to
create. Once this limit is reached, the node will be blocked
from creating new threads. By default, this parameter is set to
infinity.
Int32 num_threads

// (optional) this is the list of custom parameters specific to
each node. The designer of each node has full freedom in the
format (type, names, number) of these parameters as long as
```

```
they're supported by protobuf3.  
repeated google.protobuf.Any node_options
```

### 5.3 Nodes Currently Included in Aupera Node Toolkit

The following are the nodes that are currently included in the toolkit. Keep in mind that we are constantly adding new nodes. Furthermore, users can very easily create their own VMSS2.0 nodes. For each node, the calculator's name (the unique identifier for this node that must be included in the calculator filed inside of your pipeline ptxt file) is mentioned as well. To receive documentation on how to create your own nodes you can write to [vmss@auperatech.com](mailto:vmss@auperatech.com).

#### 5.3.1 Stream Demux

calculator: "stream\_demux"

The role of this node is to connect to a RTSP stream, receive the packets, and perform demux operation on them. This is the first node in most pipelines and, usually, communicates with a video decoder node. This node currently accepts the following parameters:

```
// selects between "udp" or "tcp" transport methods  
string    rtsp_transport  
  
// (optional) normally, the demux node might spend some time  
(around 1~2s) to calculate the actual fps of an input stream.  
This option can specify the fps to the demux node to avoid  
spending this time  
float     force_fps  
  
// if set to true, the demux node will only send the I frame  
packet to the decoder, otherwise it will send all packets  
bool      iframe_extract  
  
// if set to true, then demux node will try to reconnect the  
input stream when network quality is poor or when eof is  
received  
bool      auto_reconnect
```



### 5.3.2 Video Decoder

calculator: "x86\_decode"

The role of this node is to receive the packets from a demux node and decode them. We currently support X86 (software), AMD/Xilinx Alveo U30 (hardware), and Aupera V205 (hardware) decoding. The decoder can provide the frames in any scale (using hardware scaling is available) and in any color format (using hardware color conversion if available). Currently, h264, h265, and mpeg4 compression formats are supported. This node currently accepts the following parameters:

```
// decoder name, supports u30_dec_h2645 or v205_dec_h2645 or
x86_soft_decoder
string    name

// support multiple output picture streams with different
resolution, if set to 0, then use the same resolution with input
stream
repeated uint32 ow
repeated uint32 oh

// support multiple output picture streams with different pixel
format, supported: "RGB24" or "BGR24" or "NV12" or "I420",
default use NV12 as output pixel format
repeated string opixfmt

//decoder buffer queue size. Once this size is reached, no more
frames will be queued.
uint32    queue_size

// decoder enable low_latency or not, it can only be set to true
if input stream does not contain B frame. If this is the case,
and this option is enabled then decoder will output the frames
as soon as possible
bool      low_latency
```

### 5.3.3 Stream Mux

calculator: "stream\_mux"

The role of this node is to receive the encoded frame from a video encoder node and pass it in an RTSP stream. Alternatively, this node can save the output video to a file. This is usually the last node in pipelines that save output videos. The mux node must

always be connected to a graph-level output stream. If the server sets this output stream to an IP address, then the result will be transmitted over RTSP. If the server sets this to a file path, then the results will be saved as a video. Note that the server looks at the ptxt file passed through the -o parameter to the *avaser* command to determine where to set the destination for the mux node. For example, if the command that is running the pipeline is as follows:

```
avaser -i input.ptxt -o output.ptxt -c pipeline.ptxt
```

Then, if the output.ptxt contains valid URLs similar to those below, the results are sent over the RTSP, stream:

```
output_urls: "rtsp://10.10.190.128:554/out1"
```

However, if the output.ptxt contains a valid file path similar to below, the results is saved to disk:

```
output_urls: "/tmp/output_video.mp4"
```

This node currently accepts the following parameters:

```
// selects between "udp" or "tcp" transport methods
string    rtsp_transport

// if set to true, then demux node will try to reconnect the
input stream when network quality is poor or when eof is
received
bool      auto_reconnect
```

### 5.3.4 Video Encode

calculator: "x86\_encode"

The role of this node is to receive the frames and compress them into video packets. As such, this node is usually followed by a mux node. Currently, we support X86 (software), AMD/Xilinx Alveo U30 (hardware), and Aupera V205 (hardware) encoding. Also, h264, h265, and mpeg4 formats are currently supported. This node accepts the following parameters:

```
// encoder name, support v205_enc_h264/v205_enc_h265,
x86_enc_h264/x86_enc_h265/x86_enc_mpeg4
string name

// encoder width and height, if set to 0, then use the same
```

```
resolution with input stream
uint32 w
uint32 h

// (optional) the fps of the output video can be supplied.
Otherwise, we'll try to match this to the fps of the input rtsp
stream.
float fps

// encoder buffer queue size. Once this size is reached, no more
frames will be queued
uint32 queue_size

// if set to true then different B frame number between two P or
I frames are assigned
bool    b_adapt

// maximum B frame number between two P or I frames
uint32 bframes

// the interval of two I frames (i.e., for the entire group of
frames)
uint32 gop_size

// output video bitrate, specified in (bit/s)
uint32 bitrate

// currently supports "default", "low-latency-B", "low-latency-
P", "dynamic"
string gop_mode

// currently supports "CBR", "VBR", "CRF"
string rc_mode

// can improve the performance of single stream encoding by
using multiple threads
uint32 threads
```

### 5.3.5 Video Filter

calculator: "ff\_vfilter"

The goal of this node is to adjust the video streaming parameters such as dimensions, fps, color format, etc., as efficiently as possible. This node currently supports the following parameters:

```
// the pixel format of the output video stream. Such as "I420",  
etc.  
string opixfmt;  
  
// width of the output video stream to resize the output frames  
to. If both this parameter and the oh parameter are provided,  
roi parameters (roi_x, roi_y, roi_w, and roi_h) will be ignored.  
uint32 ow;  
  
// height of the output video stream to resize the output frames  
to. If both this parameter and the ow parameter are provided,  
roi parameters (roi_x, roi_y, roi_w, and roi_h) will be ignored.  
uint32 oh;  
  
// fps of the output video stream. If larger than the fps of the  
input stream, then interpolation is required.  
float ofps;  
  
// output buffer queue size. Once this size is reached, no more  
frames will be queued. If not provided infinity is assumed.  
uint32 queue_size;
```

### 5.3.6 Object (box) Detector

calculator: "box\_detector"

The role of this node is to run most of the object (box) detectors available on AMD/Xilinx Model Zoo. The user can specify the type (SSD, YoloV2, YoloV3, TinyYolo, RefineNet, faceDetect, etc) and the name of the specific kernel to be used. The assumption is that the model along with its runtime prototxt config (for AMD/Xilinx Model Zoo models, you can find this file provided along with the xmodel, please refer to an example provided [here](#)) file inside is placed on the machine running the object detector node in **/usr/share/vitis\_ai\_library/models** in a folder matching the kernel name inside the AVAS docker.

This node also gives users the ability to determine whether the frames should be returned in the same order that they are received or not. This is controlled by the parameter `return_frames_in_order`.

If `return_frames_in_order = true`:

If there is only a single (frame) input stream is provided, then the behavior is controlled based on the provided number of output streams as follows:

- If no output stream is specified, the node will visualize the detected bounding boxes on the frame and write the frame to disk (at the provided task directory path) with the following name: **frame-#\_pts-#\_time-#.jpg**. For example, frame 100 with pts 1000000 with time stamp 9999999 will be saved as `frame-100_pts-1000000_time-9999999.jpg`
- If there is at least one output stream is provided, the detected bounding boxes will be returned as a stream of `VinfMetaData` objects.
- If there are two output streams provided, the first input stream will contain the detections (in the form of `VinfMetaData`), and the second input stream will contain the frames. The frames will not be modified in any way (i.e., no drawing of the detected bounding boxes).

If there several (frame) input streams provided, then the behavior is controlled based on the provided number of output streams as follows:

- If no output stream is specified, the behavior is the same as above.
- If only a single output stream is specified, a runtime error is thrown
- If the specified number of outputs is the same as the specified number of inputs, then the detected bonding boxes of each stream are returned in a `VinfMetaData` stream. The order of the output streams will be the same as the input streams.
- If the specified number of outputs is exactly double the specified number of inputs, then aside from the detected bounding boxes that are returned in `VinfMetaData` streams, the original frames are returned as well. For example, if there are 5 inputs streams and 10 output streams, then the outputs streams 1 to 5 will contain the detected bounding boxes (i.e., `VinfMetaData` streams) of the input streams 1 to 5 respectively, and output streams 6 to 10 will contain the original frames of input streams 1 to 5 respectively. In other words, the detected bounding boxes of input stream index  $n$  (with index 0 corresponding to the first input stream) will be returned in output stream index  $n$ , while the frames of input stream index  $n$  will be returned in output stream index  $(n + \text{number of input streams})$ .

If `return_frames_in_order = false`:

If there is only a single (frame) input stream is provided, then the behavior is the same as above (based on number of outputs) aside from the fact that there are no guarantees on the order with which the frames and detections are returned.

If more than one input stream is provided, then the behavior is controlled based on the provided number of output streams as follows:

- If no output stream is specified, the node will visualize the detected bounding boxes on all the frames of all the streams and write the frame to disk (at the provided task directory path) with the following name: **stream-#\_frame-#\_pts-#\_time-#.jpg**. For example, frame 100 from the fifth stream with pts 1000000 with time stamp 9999999 will be saved as **stream-5\_frame-100\_pts-1000000\_time-9999999.jpg**
- If there is at least one output stream is provided, the detected bounding boxes of all the streams will be returned as a stream of `VinfMetaData` objects. In this way, the frames from different input streams will be merged into a single `VinfMetaData` output stream (i.e., neither the frames nor the streams will be in order).
- If two output streams are provided, aside from the detections (in the form of `VinfMetaData`), the input streams (frames) are returned as well. The frames will not be modified in any way (i.e., no drawing of the detected bounding boxes). In this case, the frames of all the input streams will be merged into a single output frame stream.
- If the number of output streams is equal to the number of input streams + 1, then aside from the `VinfMetaData` streams containing the detected bounding boxes, all the input streams are returned in their original format (i.e., in individual streams as well).

This node accepts the following parameters:

```
// the message format specifying the pixel mean subtracted from
// all the pixels of the input frame
message Mean {
    float r;
    float g;
    float b;
}
```

```
// the message format specifying the scale multiplied to
all pixels of the input frame
message Scale {
    float ch1;
    float ch2;
    float ch3;
}

// the message format specifying the detection confidence
threshold applied to each of the classes for the network
message LabelConfidence {
    int32 label;
    float confidence;
}

// the message format specifying the nms (none max suppression)
threshold applied to each of the classes for the network
message InterClassNms {
    float threshold;
    repeated int32 labels;
}

// pixel mean subtracted from all the pixels of the input frame
Mean mean;

// pixel scale multiplied to all pixels of the input frame
Scale scale;

// detection confidence threshold applied to each of the classes
for the network
repeated LabelConfidence label_confidence;

// the nms (none max suppression) threshold applied to each of
the classes for the network
repeated InterClassNms inter_class_nms;

// detection interval, value of 1 means the network is run on
every frame, value of 2 means the detection is run on every
other frame, value of 3 means the detection is run on every
third frame, etc
```

```
int32 detect_interval;

// the type of the detector to be used, we currently support
SSD, YoloV2, YoloV3, TinyYolo, RefineNet, FaceDetect, and
several others
string detector_type;

// name of the specific kernel to be used. The assumption is
that the model is placed on the machine running the object
detector node in /usr/share/vitis_ai_library/models in a folder
matching the kernel name
string kernel_name;

// in case of an obfuscated network, this will be the obfuscated
string token (in this case, kernel_name parameter is not
needed)
string obfuscated_token;

// whether the node should resize the input frame to the input
dimensions of the network. This is set to true in most cases,
unless the frame dimensions happen to be exactly what the
network requires
bool need_preprocess;

// logs timing (latency) information
bool log_performance;

// whether to letter box the input image or not. If set true,
letterboxing is done while maintaining the aspect ratio of the
original frame
bool run_on_letterboxed_img;

// when set to true, the black frames are ignored (the
frame_number is not incremented, and these frames are not passed
to the detector). This is when the rtsp stream is from a video
that has black padding at its beginning or end. Usually, this is
used when trying to match the performance on a video to that of
the rtsp stream of the same video.
bool ignore_black_frames;
```



```
// batch size to use for running the model, if not supplied
batch size of 1 is assumed. If the provided value is larger than
the batch size that the hardware supports, this value is capped
(to what the hardware supports)
int32 batch_size;

// if set to true a batch is only passed to the detector once
its size reaches the specified batch size (or when the
batch_collection_timeout_ms is reached). If set to false, frames
are passed to the detector as soon as they arrive (so the
specified batch size is only applied if enough frames have been
collected while the detector is processing the previous batch).
bool force_batch_size;

// number of milli-seconds the node will wait on a batch of
frames to be collected. Once this number is reached, the
collected batch is sent to the detector regardless of its size.
int32 batch_collection_timeout_ms;

// if true, then the ordering of the frames within the same
stream and the ordering of the streams will be maintain (i.e.,
the output streams will follow the same ordering). When using a
single thread, the ordering is always maintained. However, when
using multiple threads, not maintaining the order (setting this
parameter to false) will improve performance.
bool return_frames_in_order;

//number of threads to be used for running a detection. Multi-
threaded processing loses the order of the frames (and the order
of the streams); so if in order processing is required, the
process_frames_in_order must be set to true. Single threaded
detection will always maintain the original ordering (of the
frames and streams). If this parameter is not provided value of
1 is assumed.
int32 detection_threads;
```

### 5.3.7 Object Tracker

calculator: "box\_tracker"

The goal of this node is to support multi-object tracking on a single stream. We support several types of trackers including Sort++, DeepSort. DeepSort, requires an encoding of the objects to be provided; as such, it's the most accurate tracking method available in this node. However, accuracy and latency are controlled by the encoder network (i.e., it requires the encodings to perform similarity matching, which needs to be run outside of the tracker). Sort++, on the other hand, does not require encoding of the objects (to perform similarity) which makes it the fastest tracker supported by this node (with descent accuracy in most conditions).

This node has the capability of receiving the detect\_interval that the detector node uses via side packets. In this case, on frames that the detector has not been run, the tracker will make predictions as to where the objects are. On frames, that detector is run, the tracker will use the detected bounding boxes to correct its estimation models.

The first input stream of this node is always assumed to be of the type VInfMetaData containing the detected bounding boxes. When using DeepSort, the first stream must contain the encodings of the detected objects as well. If present, the second input stream is assumed to be the video stream (of frames) corresponding to the detected bounding boxes. If two streams are provided, then the synchronization flags are mandatory to ensure that the detected bounding boxes (from the first stream) correspond to the frame (from the second stream) if within the detect interval.

This node only provides single stream/camera tracking, for multi streams tracking you should use the provided multi stream tracker (i.e., reid) node instead. This node will be provided in our future release.

The logic for the output of the tracker node is as follows:

- If no output stream is specified, but a second input stream (i.e., video frames) is provided, the node will visualize the detected (and predicted) bounding boxes on the frame and write the frame to disk (at the provided task directory path) with the following name: **frame-#\_pts-#\_time-#.jpg**. For example, frame 100 with pts 1000000 with time stamp 9999999 will be saved as **frame-100\_pts-1000000\_time-9999999.jpg**
- If no output stream is specified, and there is only a single input stream (i.e., just the detected bounding boxes) is provided, a runtime error is thrown.
- If more than one output stream is specified, the first one will always be of the type VInfMetaData containing the detected (and predicted) bounding boxes. If there is more than one input streams (i.e., a stream of frames is also supplied as input)

then the second output stream will contain the input frames without any modifications.

This node accepts the following parameters:

```
// type of the tracker to be used currently we support Sort++,
// and DeepSort among others
string tracker_type;

// predicted bounding boxes with areas smaller than this
// threshold (in terms of square pixels) will be ignored
int32 min_object_area_th;

// speed buffer parameter of the MOSSE tracker (not used by
// Sort++ or DeepSort trackers)
int32 speed_buffer_max_size;

// Maximum number of detect intervals that the tracker will keep
// a track that does not get matched with any new detections alive
int32 max_keep_alive;

//minimum number of matched detections required before a track
// is considered reliable
int32 min_hits

// used by sort++ and deepSort trackers. If a detected object
// achieves a total affinity score that is higher than this
// threshold with a tracker, it will be considered a match (will be
// used update the tracker state).
float affinity_threshold;

// used by sort++ and deepSort trackers. Weight of the shape
// similarity score inside the total affinity score
float shape_weight;

// used by sort++ and deepSort trackers. Weight of the position
// similarity score inside the total affinity score
float position_weight;
```

```
// used by sort++ and deepSort trackers. Weight of the
appearance (i.e., encoding vector) similarity score inside the
total affinity score
float appearance_weight;

// used by sort++ and deepSort trackers. If the shape similarity
score between a detected bounding box and a tracker is larger
than this threshold, a match will not happen (regardless of all
other scores)
float shape_dist_max;

// used by sort++ and deepSort trackers. If the position
similarity score between a detected bounding box and a tracker
is larger than this threshold, a match will not happen
(regardless of all other scores)
float position_dist_max;

// used by sort++ and deepSort trackers. Toggling between exp
cost and weighted sum cost
bool use_exp_cost;
```

### 5.3.8 Image Classifier

calculator: "box\_classifier"

The role of this node is to run any of the classifier networks available on Xilinx model zoo. The user can specify the type (ResNet, Inception, SqueezeNet, etc.) and the name of the specific kernel to be used. The assumption is that the model is placed on the machine running the object detector node in **/usr/share/vitis\_ai\_library/models** in a folder matching the kernel name.

If the only a single (frame) input stream is provided, containing full frames of cropped detected objects (that the classifier must run on), then the behavior is controlled based on the provided number of output streams as follows:

- If no output stream is specified, the node will save the frames (or cropped images) with the detected class in the name according to the following format: **stream-#\_frame-#\_pts-#\_time-#.jpg**. For example, the fifth crop of frame 100 with pts 1000000 with time stamp 9999999, with the detected class "car" will be saved as **frame-100\_pts-1000000\_time-9999999.jpg**. Bounding boxes and the labels are overlaid on the image.

- If there is at least one output stream is provided, the detected classes will be returned as a stream of `VinfMetaData` objects.
- If more than one output stream is provided, aside from the classes (in the form of `VinfMetaData`), the input stream (crops or frames) is returned as well. The frames (or crops) will not be modified in any way (i.e., no drawing of the detected bounding boxes).

If more than one input stream is provided, then the user must specify whether they require the resulting classed to be returned in separate streams or not using the **`return_in_order`** parameter. If this parameter is set to true, then:

- If no output stream is specified, the node will save the frames (or cropped images) with the stream index and detected class in the name according to the following format: **`stream-#_frame-#_pts-#_time-#.jpg`**. For example, the fifth crop of frame 100 from 6<sup>th</sup> stream with pts 1000000 with time stamp 9999999, with the detected class “car” will be saved as **`crop-5_class_car_stream-6_frame-100_pts-1000000_time-9999999.jpg`**
- If the number of outputs is equal to number of image input streams, then classifier node sends classifications in the form of `VinfMetaData` to the output streams. There is a one-to-one relationship between the input frames streams and output streams
- If the number of output streams is equal to twice the number of image input streams, then aside from the `VinfMetaData` streams containing the detected classes boxes, all the input streams are returned in their original format (i.e., in individual streams as well).

If the **`return_in_order`** parameter is set to true, then:

- If no output stream is specified, the behavior is the same as above.
- If only a single output stream is specified, a runtime error is thrown
- If the specified number of outputs is the same as the specified number of inputs, then the detected classes of each stream are returned in a `VinfMetaData` stream. The order of the output streams will be the same as the input streams.
- If the specified number of outputs is exactly double the specified number of inputs, then aside from the detected classes that are returned in `VinfMetaData` streams, the original frames (or crops) are returned as well.

For example, if there are 5 inputs streams and 10 output streams, then the first 5 outputs streams are the detected bounding boxes (i.e., VinfMetaData streams) and the last 5 outputs streams are the original frames.

This node accepts the following parameters:

```
// the type of the classifier to be used, we currently support
ResNet, Inception, SqueezeNet, and several others
string classifier_type;

// name of the specific kernel to be used. The assumption is
that the model is placed on the machine running the object
classifier node in /usr/share/vitis_ai_library/models in a
folder matching the kernel name
string kernel_name;

// whether the node should resize the input frame to the input
dimensions of the network. This is set to true in most cases,
unless the frame dimensions happen to be exactly what the
network requires
bool need_preprocess;

// whether to letter box the input image or not. If set true,
letterboxing is done while maintaining the aspect ratio of the
original frame
bool run_on_letterboxed_img;

// batch size to use for running the model, if not supplied
batch size of 1 is assumed. If the provided value is larger than
the batch size that the hardware supports, this value is capped
(to what the hardware supports)
int32 batch_size;

// if true, then the ordering of the frames (or crops) within
the same stream and the ordering of the streams will be maintain
(i.e., the output streams will follow the same ordering). When
using a single thread, the ordering is always maintained.
However, when using multiple threads, not maintaining the order
(setting this parameter to true) will improve performance.
```

```
bool return_in_order;

// number of threads to be used for running a classification.
Multi-threaded processing loses the order of the frames (and the
order of the streams); so if in order processing is required,
the process_frames_in_order must be set to true. Single threaded
classification will always maintain the original ordering (of
the frames and streams). If this parameter is not provided value
of 1 is assumed.
int32 classification_threads;

// whether batch sizes are forced
bool force_batch_size;

// the timeout of each batch. If batching takes up to this time
even though batch_size is not reached, the batch will be
submitted
uint64 batch_collection_timeout_ms;

// whether or not classifier uses detections as inputs
bool use_detections;

// logs timing (latency) information
bool log_performance;

// maximum size of queue that classifier library uses
int32 max_classification_lib_q_size;

// maximum allowed cache size for frames. This option is
meaningful when force_batch and return_in_order is true. In the
case that there are no detections in several consecutive frames
of the input, this prevents the output to be too far behind the
input. The default value is 8

int32 max_frame_cache_size;
```

### 5.3.9 Object (box) Visualizer

calculator: "box\_visualizer"

The goal of this need is to visualize the output of Object (box) Detector, Object tracker, and Image Classifier nodes. This node has different versions that use hardware accelerated methods (on platforms that support this functionality) and software (OpenCV) methods on platforms that don't support hardware acceleration. Based on these options, the behavior is as follows:

- If `input_type` is `INPUT_TYPE_DETECTION`, then the assumption is that the first input stream is of the type `VinfMetaData` containing the detected bounding boxes while the second input stream contains the frames.

In this case, if there is no output stream specified, then the frames with the bounding boxes visualized on them will be written to disk according to **frame-#\_pts-#\_time-#.jpg**. For example, frame 100 with pts 1000000 with time stamp 9999999 will be saved as **frame-100\_pts-1000000\_time-9999999.jpg**.

If an output stream is specified, then it will contain the frames with the detected bounding boxes visualized on them.

- If `input_type` is `INPUT_TYPE_CLASSIFICATION`, then the assumption is that the first input stream is of the type `VinfMetaData` containing the detected classifications while the second input stream contains the frames (or the crops) that generated the classifications.

In this case, if there is no output stream specified, then the frames (or the crops) will be written to disk according to **crop-#\_class-str\_frame-#\_pts-#\_time-#.jpg**. For example, the fifth crop of frame 100 with pts 1000000 with time stamp 9999999, with the detected class "car" will be saved as **crop-5\_class\_car\_frame-100\_pts-1000000\_time-9999999.jpg**

If an output stream is specified, then it will contain the frames (or crops) with the classifications and their bounding boxes (in the case that it applies) overlaid on them starting from the top left corner of the frame (or crop) + an offset.

This node accepts the following parameters:

```
// the message format specifying the color to be used for
drawing bounding boxes or text
message Color {
  float r;
  float g;
  float b;
}
```



```
// the message format specifying color to be used for specific
classes
message ClassColor {
    Color color;
    int32 label;
}

// the message format specifying the offset to be used for the
location of drawing texts
message Offset {
    float x;
    float y;
}

// this is a type that determines the input type of the node.
indicating if it is detections or classifications
enum InputType {
    INPUT_TYPE_DETECTION;
    INPUT_TYPE_CLASSIFICATION;
}

// this is the variable that determines the input type based on
the enum type above
InputType input_type;

// This determines the color of the box in the case that
input_type == INPUT_TYPE_DETECTION
Color box_color;

// This declares an array of colors for classifications. Each
element of this repeated message indicates what color that
specific classification should be have. This color is both used
for the text and the bounding box. This option is only valid if
input_type == INPUT_TYPE_CLASSIFICATION.
repeated ClassColor class_color;

// In the case that some classification color for a specific
class is not defined in class_color array, the color will
default to this. This option is only valid if input_type ==
INPUT_TYPE_CLASSIFICATION.
```

```
Color default_class_color;

// Determines the offset of the text from the top-left corner of
the bounding box. This option is only valid if input_type ==
INPUT_TYPE_CLASSIFICATION.
Offset text_offset;

// Determines the thickness of the box. This option is only
valid if input_type == INPUT_TYPE_CLASSIFICATION.
int32 box_thickness;

// Determines the text_size. This option is only valid if
input_type == INPUT_TYPE_CLASSIFICATION.
int32 text_size;

// This determines the font of the text for classifications
according to HersheyFonts. This option is only valid if
input_type == INPUT_TYPE_CLASSIFICATION.
int32 font;

// This determines the font size. This option is only valid if
input_type == INPUT_TYPE_CLASSIFICATION.
double font_scale;

// This determines the font thickness. This option is only valid
if input_type == INPUT_TYPE_CLASSIFICATION.
int32 font_thickness;

// This determines the line_type used in classification text.
the line_type is according to #LineTypes. This option is only
valid if input_type == INPUT_TYPE_CLASSIFICATION.
int32 line_type;
```

### 5.3.10 Image Stream calculator

calculator: "image\_stream"

The goal of this node is to give the ability to the user to stream a set of images instead of a live camera/RTSP stream. This gives the flexibility for testing certain scenarios as well as pipelines that require a directory of images.

This node has a single input which is a dummy stream address. This address is not used anywhere so best is to use some arbitrary dummy rtsp stream that does not exist.

This node has a single output that similarly to decode node outputs a stream of GvisVframes. The images are iterated through in alphabetical order. After the last image is reached, then stream restarts from the first file.

Input\_type determines the type of frames to be used as input.

```
// this integer determines the frame interval between each
// image. for example for 25 fps, the value should be set to 40.
uint32 frame_interval_ms;

// this is the directory in which the images are stored
string directory;

// This is the target width of the image. If the image width is
// not as specified here, it will be scaled to fit it
uint32 width;

// This is the target height of the image. If the image height
// is not as specified here, it will be scaled to fit it
uint32 height;

// This determines the type of images in the input
enum InputType {
    // Raw Vooya images
    VOOYA_BGR = 0;
    // jpeg images
    JPEG = 1;
    // png images
    PNG = 2;
}

// instantiates InputType to fit the images in the directory
InputType input_type;
```

### 5.3.11 Video Stream calculator

calculator: "video\_stream"

The goal of this node is to use a video file to create a stream of images instead of RTSP

streams. This gives flexibility for testing pipelines when there is no camera or RTSP stream or simply when the pipeline wants to use a video file as input

This node has a single input which is a dummy stream address. This address is not used anywhere so best is to use some arbitrary dummy rtsp stream that does not exist.

This node has a single output that similarly to decode node outputs a stream of GvisVframes. After the last frame of the video is reached, then stream restarts from the beginning of the video file.

Like the demux node, this node has a side packet which sends out information like fps, dimensions, and more.

```
// If set to 0, it will use the videos fps. If not, slow-
down/speed-up the video to match the speed
float playback_fps;

// this indicates the path to the video file
string path;

// This is the target width of the image. If the image width is
not as specified here, it will be scaled to fit it. If either of
width/height is not defined or is equal to 0, then original
video width will be used
uint32 width;

// This is the target height of the image. If the image height
is not as specified here, it will be scaled to fit it. If either
of width/height is not defined or is equal to 0, then original
video height will be used
uint32 height;
```